# XVR-B3507.8.44.240515 Release Notes

Zhejiang Uniview Technologies Co., Ltd.

# XVR-B3507.8.44.240515 Release Notes

Keywords: Version information, usage notes, precautions.

**Abstract:** This document provides information about the **XVR-B3507.8.44.240515** board software, including version information, usage notes, precautions, and features.

#### **Acronym**

Acronym	Full Name
NVR	Network Video Recorder

2024-5-30 Page 1

### Contents

1 V	ersion Information·····	3
	1.1 Version Number ·····	3
	1.2 Applied Product Models	3
	1.3 Release History ·····	3
2 U	sage Notes ·····	3
3 S	oftware Features ·····	3
4 V	ersion Change Description ·····	4
	4.1 Feature Change Description	4
	4.2 Operation Change Description	5
5 R	elated Documents and Delivery Method·····	5
6 V	ersion Upgrade Guidance ·····	6
	6.1 Precautions	6
	6.2 Upgrade Procedure ·····	6
	6.3 Upgrade Through the System Interface	6
	6.4 Upgrade Through the Web Interface·····	7

### 1 Version Information

#### 1.1 Version Number

XVR-B3507.8.44.240515

### 1.2 Applied Product Models

Table 1 Applied Product Models

Product Models	Description	
XVR302-16Q3	2 HDD, 16 analog channel, 8 IP channel, H.264, H.265	
XVR302-08U3	2 HDD, 8 analog channel, 8 IP channel, H.264, H.265	

### 1.3 Release History

Table 2 Released Versions

Version No.	Basic Version No.	Released On
XVR-B3507.8.44.240515	XVR-B3507.8.42.240411	2024-05-15
XVR-B3507.8.42.240411	XVR-B3507.7.26.231023	2024-04-11
XVR-B3507.7.26.231023	XVR-B3507.7.21.230925	2023-10-23
XVR-B3507.7.21.230925	XVR-B3507.6.35.230818	2023-09-25
XVR-B3507.6.35.230818	XVR-B3507.6.31.230718	2023-08-18
XVR-B3507.6.31.230718	XVR-B3507.5.26.230327	2023-07-18
XVR-B3507.5.26.230327	XVR-B3507.3.20.221208	2023-03-27
XVR-B3507.3.20.221208	XVR-B3507.3.16.221028	2022-12-08
XVR-B3507.3.16.221028	Initial release	2022-10-28

## 2 Usage Notes

None.

## 3 Software Features

Table 3 Software Features

Service	Feature	
Audio and video decoding	H.264 and H.265, up to 16Mbps bit rate.	
Data storage	Local storage of recordings in hard disk(s).	
Web-based management	Web-based user interface for device configuration and management.	

# 4 Version Change Description

## 4.1 Feature Change Description

Table 4 XVR-B3507.8.42.240411 Feature Changes

Item	Feature	Description		
	Image mode and noise reduction	Supports image noise reduction. You can set different image modes for various periods of time in the same scene.		
	Optimized OSD effect	Improves the image effect on the Web's live view and playback interfaces to prevent OSD from stretching and deforming.		
	Storage mode switch	Allows to change the storage mode, so as to store more data when the storage space is limited.		
	Allows to disable UMD for multiple analog cameras in batches	UMD supports copy function to realize batch operations, improving the efficiency.		
	Smart dual light	Supports smart dual light after connecting Uniview analog cameras.		
Newly	The local interface allows to set the image display ratio	By setting the image display ratio, the local interface can output the optimal image to fit the window in various scenes, preventing image stretch due to the access of cameras with different display size.		
added features	Analog cameras support PAL/NTSC	Allows to configure the PAL/NTSC video standard for multiple analogy cameras in batches.		
	Supports SD recordings backup	On the Playback interface, users can clip and download SD recordings.		
	Supports sending an email to the specified email address when an alarm is triggered	This function allows to specify the email recipient(s) for various alarms when alarms occur.		
	Supports 3K analog cameras of other manufacturers	Supports 3K, 2960*1664@20fps resolution.		
	Supports loading service without plug-in installed	The functions on the Web interface can be used normally even if the plugin is not installed.		
	Supports searching playback by motor vehicle, non-motor vehicle, and human body	User can search playback by object type so as to quickly view the desired object recordings, improving the search efficiency.		
Ontimized	Optimized prompts for retrieving the password	Before modification, the interface shows the specific app and path to retrieve the password. After modification, uses can scan the QR code with the phone to retrieve the password, easy and convenient.		
Optimized features	Supports sending one email with alarm information and image to the specified recipient(s) when an alarm occurs	In the previous version, the NVR will send two emails when an alarm occurs, including the first email without snapshot and the second email with snapshot. In this version, the NVR will send an email attached with snapshot(s) and alarm information when an alarm occurs.		
Deleted features	/	/		

Table 5 XVR-B3507.7.20.230908 Feature Changes

Item	Feature	Description	
Newly	U-code for the analog camera	Supports advanced and basic U-code modes for the analog camera.	
added features	NVR-side SIP	Supports NVR-side SIP.	
	Auto frame rate(fps)	The analog camera's frame rate automatically switches as the resolution changes, so as to maximize encoding performance.	
Improved features	None	None	
Deleted features	None	None	

#### Table 6 XVR-B3507.5.26.230327 Feature Changes

Item	Feature	Description	
Newly	UMD	Supports ultra motion detection, which allows user to configure detection alarm for pedestrians and motor vehicles, and search the snapshots and recordings of pedestrians and motor vehicles.	
added features	Privacy mask	Supports privacy mask.	
	Snapshot	Supports snapshot via analog camera.	
Improved features Optimized default live view window of 4/8/16-cha optimized to 4/8/16 screens.		The default live view window of 4/8/16-channel XVR is respectively optimized to 4/8/16 screens.	
Deleted features	None	None	

### 4.2 Operation Change Description

None

## 5 Related Documents and Delivery Method

Table 7 Related Document List

Manual Name	Manual Version	Delivery
Network Video Recorders Quick Guide	V1.00	Deliver with device.

## 6 Version Upgrade Guidance

#### 6.1 Precautions

- This software system includes a software program mirror (Program.bin).Before you start upgrade, please back up configuration data through the system or Web interface in case the upgrade fails.
- Maintain proper network connection and power supply during the upgrade.

### 6.2 Upgrade Procedure

The version can be upgraded through the system interface and the Web interface, both support cloud upgrade.

### 6.3 Upgrade Through the System Interface


The system interface provides two options for upgrading the system software: local upgrade using a USB drive and cloud upgrade.

#### 1. Local upgrade

Before you start, copy the correct upgrade file to the root directory of the USB drive.

- (1) Plug the USB drive into the USB interface on the NVR.
- (2) Log in to the system interface as "admin".
- (3) Click Maintain>Upgrade.
- (4) Click **Upgrade**, select the upgrade file from the drop-down list, and then click **Upgrade**. A prompt message appears.
- (5) Click OK.

Figure 1 Prompt Message



(6) The NVR will restart automatically when the upgrade is completed.

#### 2. Cloud upgrade

Before you start, check that the NVR is correctly connected to the public network.


- (1) Click **Maintain>Upgrade**, and then click **Check** to check for the latest version.
- (2) Click **Upgrade** after a newer version is detected.

### 6.4 Upgrade Through the Web Interface

Perform the following steps to upgrade through the Web interface:


- (1) Log in to the Web interface as "admin".
- (2) Click Settings>Maintenance>Maintenance.

Figure 2 System Maintenance



- Click Browse right to the Upgrade field, select the Program.bin file to upgrade, and then click Upgrade.
- (4) If the NVR is connected to the public network, you may also click **Check** to perform a cloud upgrade. If a newer version is detected, a prompt message will appear. Click **OK** to start upgrade.

Figure 3 Prompt Message



(5) The NVR will restart automatically when the upgrade is completed.

#### Version Upgrade Disclaimer

- By setting or installing this program in any way you agree to all of the following terms and conditions. Your
  downloading or using the program means you acknowledge your full understanding and acceptance of the
  following terms and conditions. If you do not agree to any of the following terms, you shall not use the
  program and you must cease installing and delete the program immediately.
- 2. The upgrade program is only applicable to the intended regions and product models. Before upgrade or update, please read the release notes carefully to make sure the program is applicable to your region and product model. You will be fully liable and responsible for all the consequences of device abnormality and related maintenance costs caused by your improper operations.
- 3. Uniview owns or is legally authorized to own all rights and IPRs (Intellectual Property Rights) of the program and the supplied release notes.
- 4. Software upgrades are for the optimization of product functions and do not mean there is defect.
- 5. You must strictly follow instructions in the release notes during the upgrade process, otherwise you are responsible for the possible consequences and related maintenance costs.
- 6. You shall not engage in any of the following activities, otherwise you would be liable for infringement and responsible for any adverse consequences arising therefrom.
- 6.1 Copy the program (exclude the reasonable and necessary copies for internal backups);
- 6.2 Exclude this statement when using the program or transfer the program to any third party;
- 6.3 Modify the program or its derivatives;
- 6.4 Reverse engineer, decompile or disassemble this program.
- 7. The program is only intended for authorized users. Its architecture, organization and source code are valuable trade secrets and confidential information owned by Uniview and its authorized parties. You agree not to provide or disclose any confidential information contained in or derived from the software to any third party. No part of this document may be excerpted, reproduced, or distributed in any form by any entity or individual without written consent from our company.